

Automation in LTspice using `.param`, `.step`, and `.meas`

Prepared for LTspice Users
by Taranga Talukder

December 14, 2025

1 Introduction

LTspice provides powerful automation commands that allow you to:

- Define variables (`.param`) for component values.
- Sweep parameters over a range of values (`.step`).
- Automatically measure results (`.meas`) such as maximum voltage, rise time, and RMS.

These commands help reduce manual simulation effort and make experiments reproducible.

2 1. The `.param` Command

The `.param` command defines a variable to be used in component values.

Syntax:

`.param <name>=<value>`

Example:

```
1 .param Rval=1k  
2 R1 N001 N002 {Rval}
```

Explanation:

- ‘Rval’ is the resistor parameter.
 - ‘Rval’ is used in the component, so changing the parameter automatically updates the circuit.
-

3 2. The .step Command

The `.step` command is used to sweep a parameter over a range of values.

Syntax:

```
.step param <param_name> <start> <stop> <increment>
```

Example:

```
1 .step param Rval 1k 5k 1k
```

This will run 5 simulations with $Rval = 1k, 2k, 3k, 4k, 5k$.

List Sweep Example:

```
1 .step param Rval list 1k 2k 4k 8k
```

This simulates for $Rval = 1k, 2k, 4k, 8k$.

4 3. The .meas Command

The `.meas` command allows automatic extraction of values from simulations.

Syntax:

```
.meas <tran/freq> <name> <what_to_measure> <expression>
```

Common Examples:

- Maximum voltage:

```
1 .meas tran Vmax MAX V(N002)
```

- Time when voltage reaches a value:

```
1 .meas tran Tcross WHEN V(N002)=2
```

- RMS voltage:

```
1 .meas tran Vrms RMS V(N002)
```

Integration with Parameter Sweep:

```
1 .meas tran Vpeak PARAM Rval MAX V(N002)
```

- Measures max voltage for each value of Rval during a sweep.

5 4. Simple Example: Sweep Resistor and Measure Max Voltage

```
1 * Simple Example
2 V1 N001 0 DC 5
3 R1 N001 N002 {Rval}
4 C1 N002 0 1u
5
6 .param Rval=1k
7 .step param Rval 1k 5k 1k
8 .tran 0 1ms
9 .meas tran Vmax PARAM Rval MAX V(N002)
10 .end
```

Explanation:

- Defines ‘Rval’ as a parameter.
 - Sweeps resistor from 1k to 5k.
 - Measures the maximum voltage at node N002 for each resistor value.
 - Results are shown in the SPICE error log.
-

6 5. Advanced Example: Sweep Resistor and Capacitor, Measure Multiple Metrics

```
1 * Advanced Automation Example
2 V1 N001 0 DC 5
3 R1 N001 N002 {Rval}
4 C1 N002 0 {Cval}

5
6 .param Rval=1k
7 .param Cval=1u
8
9 .step param Rval 1k 5k 1k
10 .step param Cval 1u 5u 2u
11 .tran 0 5ms
12
13 .meas tran Vpeak PARAM Rval PARAM Cval MAX V(N002)
14 .meas tran Trise PARAM Rval PARAM Cval TRIG V(N002) VAL
   =0.5 TARG V(N002) VAL=4.5
15 .meas tran Vrms PARAM Rval PARAM Cval RMS V(N002)
16 .end
```

Explanation:

- Sweeps Rval from 1k to 5k in steps of 1k.
- Sweeps Cval from 1u to 5u in steps of 2u.
- Measures:

1. V_{peak} → Maximum voltage
 2. T_{rise} → Rise time from 0.5V to 4.5V
 3. V_{rms} → RMS voltage
- All results are automatically stored in the SPICE error log.
-

7 6. Tips for Automation

- Use curly braces {} when referencing parameters in components.
- ‘.step’ can sweep multiple parameters; LTspice does a nested sweep automatically.
- ‘.meas’ is extremely flexible; it can calculate max, min, RMS, rise/fall time, and even formula-based expressions.
- Always check the **SPICE error log** to see results after a sweep.

8 References

- LTspice User Guide: <https://www.analog.com/en/design-center/design-tools-and-calculators/ltspice-simulator.html>